


It is assumed that the GL's T1E1 Hardware, Software, and License installations are already performed by referring to the respective T1E1 hardware Quick Installation Guide (for example, T1E1-Dual-USB-tProbe-Analyzer-Quick-Install-Guide.pdf). Also perform license installation for the purchased protocol analyzer software.

T1E1 HDLC Playback application is available as optional software (XX090) with the GL's T1/E1 analyzer. Users require GL's license for xx090 to integrate HDLC Playback and Analyzer with already existing T1/E1 Analyzer. Once the license has been installed properly, the application can be invoked to playback HDLC file.


## Verification

The below example depicts adding of ports and timeslots, specifying HDLC file (DCOSS.hdl) to playback the selected file.

- After successful installation of T1E1 hardware such as, tProbe, Portable USB, Universal PCI Board, Dual PCIe Express T1E1
   Boards, and Octal / Quad T1E1 PCIe Express Board.
- Double-click on the T1E1 application short-cut icon created on the desktop.
- Select Special Applications → Protocol Analysis → HDLC Playback. This will invoke Transmit HDLC window as shown below.




- Click Add to open the Select Card and Time Slot for Transmission screen
  - > Select the Card Number as 1
  - Click on **All Time Slots**, to select all timeslots on Card #1.
  - Click OK to apply the selected settings.





On the Transmit HDLC window, click on Browse button option and select the required .hdl (dcoss.hdl) file from the
installation directory.



- Continuous The HDLC frames contained in the file are transmitted continuously into the HDLC data channel.
- Limited Only the defined number of HDLC frames (entered in the Limit field) is transmitted from the designated file.
- Now, click Start to transmit the HDLC file.
- If the T1E1 Analyzer is in loopback mode, then the traffic (dcoss.hdl) transmitted on **Port #1** is looped back on to **Port #2**. The transmitted traffic can be captured on real-time basis using any of the T1E1 HDLC Protocol Analyzers. For more details, refer to **T1E1-Protocol-Analyzer-Quick-Verification-Guide.pdf**.